Connect my Gaming Console to the "CNU-Res" wireless network

Introduction

The "**CNU-Res**" wireless network is available in all residence halls for the purpose of connecting devices such as; Gaming Consoles, Streaming Media Players, SmartTVs, and other IoT devices. In order to connect these devices to the wireless network "**CNU-Res**" please follow the steps below. The "**C NU-Res**" wireless network will **NOT** support computers, smart phones, or tablets; please continue to connect those devices to eduroam for internet access.

> ⚠ Please note - when following the steps below you must be connected to eduroam in order to access the "CNU-Res" device registration page.

Table of Contents

Steps for Connecting your device to "*CNU-Res*"

(Step #1) Navigate to Registration Page - LINK

> ⚠ Please note - you must be connected to eduroam in order to access the "CNU-Res" device registration page.

- **Username** = Enter your CNU email address
- **Password** = CNU Account Password

---

(Step #2) Create Device

- **Device Name** = Enter a name of your choice
- **Device Type** = From the dropdown menu select the correct device type
- **MAC Address** = Enter your device's "WiFi" MAC Address
    - For assistance finding the MAC Address of your device please visit your manufacturers support website
- Click the "**Submit**" button when finished

⚠ Students are permitted to register up to three devices only.

(Step #3) Record the "Connection Instructions"

- After clicking the submit button you will be presented with important information required for connecting to the "CNU-Res" wireless network. You will need this information when connecting your device to the wireless network.
- **Connect to the wireless network:** CNU-Res
    - Security type = WPA2-Personal
    - Encryption type = AES
- **Encryption "Preshared Key"** = *************

(Step #4) Connecting your Gaming Console to "*CNU-Res*"

- Remember! You will need the connection instructions from the step above to connect your device to the wireless network "*CNU-Res*"

PlayStation 5

- Navigate to **Settings** > **Network** > **Settings** > **Set Up Internet Connection**

- Select the wireless network "*CNU-Res*" to connect to

- When prompted, enter the Pre-Shared Key provided to you when you registered your device

- For more information please visit PlayStation support - LINK

PlayStation 4

- Navigate to **Settings** > **Network** > **Set Up Internet Connection** and selecting **Use Wi-Fi**

- If you select **Easy**, saved wireless networks and wireless networks that have been found appear

- Select the wireless network "*CNU-Res*" to connect to

- When prompted, enter the Pre-Shared Key provided to you when you registered your device

- For more information please visit PlayStation support - LINK

Microsoft XBOX

- Press the Xbox button to open the guide

- Select **Profile & system** > **Settings** > **General** > **Network settings**

- Select **Set up wireless network**

- Select the wireless network "*CNU-Res*" from the list of available networks

- When prompted, enter the Pre-Shared Key "WiFi Password" provided to you when you registered your

device

- For more information please visit Microsoft support - [LINK](#)

Nintendo Switch

- On the Nintendo Switch console, select Settings from the HOME Menu

- Select **Internet**, and then **Internet Settings**. The Nintendo Switch will automatically search for near-by Wi-Fi signals

- Select the "*CNU-Res*" network name (SSID) from the list

- When prompted, enter the Pre-Shared Key "WiFi Password" provided to you when you registered your device

- For more information please visit Nintendo support - [LINK](#)